



PASSWORD UNLOCKER

Enjoy to Use Password Reset and Password Recovery Tools

Windows Password Unlocker User Guide

After purchased the software, please download the full version of [Windows Password Unlocker Enterprise](#) by a link from your email box in a computer that you can run as administrator. The whole Windows password recovery process can be divided to 3 big steps:

Devices you need to prepare in advance:

1. A computer run as administrator
2. A USB flash drive or a blank CD/DVD along with CD-ROM±RW drive

Overall Steps:

After download and install, take the following 3 steps to reset lost Windows password.

[Step 1: Burn a bootable password reset CD/DVD/USB](#)

[Step 2: Boot your computer from the password reset disk](#)

[Step 3: Reset your forgotten Windows password](#)

- [Reset Windows Local password](#)
- [Reset Windows Domain password](#)



PASSWORD UNLOCKER

Enjoy to Use Password Reset and Password Recovery Tools

Step 1: Burn a bootable password reset CD/DVD/USB

1. Insert a blank CD/DVD or USB flash drive in the computer
2. Create a bootable password reset disk by selecting target device and clicking Burn CD/D or Burn USB button.



3. Click **OK** when the password reset disk is created.



PASSWORD UNLOCKER

Enjoy to Use Password Reset and Password Recovery Tools



Step 2: Boot your computer from the password reset disk

Insert the created password reset CD/DVD or USB drive in the computer that you want to reset Windows password of, and then boot the computer from the password reset disk.

If you have burned password reset disk with CD/DVD, please set your locked computer BIOS to boot from CDROM, but If you have burned password reset disk with USB flash driver, please set your locked computer BIOS to boot from USB.



PASSWORD UNLOCKER


Enjoy to Use Password Reset and Password Recovery Tools

1. Insert the burned CD/DVD or USB flash drive into the locked computer.
2. Start computer and press **F2** or **Delete** to enter **BIOS Setup** interface when the computer is booting.

Note:

- ✓ Press **F2** or **Delete** immediately as the PC starts. Otherwise, you will see Windows logon screen and cannot access BIOS settings screen.
- ✓ **F2** or **Delete** is the common key able to enter BIOS. The key to access into BIOS depends on the manufacturer of the motherboard and BIOS vendors.

3. Select the **Boot** tab with the arrow keys, and then select **Boot Device Priority** and press **Enter**.



4. Directly choose **CDROM** as **1st boot device** with arrow keys or back to **Boot Device Priority**, and you'll find the USB drive. Choose **1st boot device to USB**, and then press **F10** to save settings. And the computer will restart with the changed settings automatically.

Note: If you cannot find USB drive after entering Boot Device Priority, you'll need to enter Hard Disk Drives to adjust USB to 1st Drive at first.



PASSWORD UNLOCKER

Enjoy to Use Password Reset and Password Recovery Tools



5. Press **F10** to save settings and exit. The computer will restart automatically with changed BIOS settings.

Step 3: Reset your forgotten Windows password

After booting the password reset disk correctly, you are able to **Reset Windows Local password** for Windows 7/Vista/XP/2008/2003/2000 or **Reset Windows Domain Password** for Windows 2008(R2)/2003(R2)/2000 servers that act as domain controllers.

- **Reset Windows Local password**



PASSWORD UNLOCKER

Enjoy to Use Password Reset and Password Recovery Tools

1. Select operating system installation you want to reset password of.



2. Select an option to reset forgotten Windows local password.

Option 1: Remove Windows Local Password - If you decide to remove your forgotten Windows password, please do as follows:

- 1). Select the target user account and choose **Remove Windows Password**, then click **Next**.



PASSWORD UNLOCKER

Enjoy to Use Password Reset and Password Recovery Tools



2). Click **Next** if you are sure to password of the user account listed on the interface.

Note: If the user account is disabled or locked out, it will be enabled or unlocked automatically.



PASSWORD UNLOCKER

Enjoy to Use Password Reset and Password Recovery Tools



3. Click **Reboot** to restart computer and log into the user account without password. You can also click **OK** to return to the main interface for other jobs.

Note: Please remove the bootable disk before Windows restarts.



PASSWORD UNLOCKER

Enjoy to Use Password Reset and Password Recovery Tools



Option 2: Change Windows Local Password - If you decide to change your forgotten Windows password, please do as follows:

1). Select the target user account and choose **Change Windows Password**, then click **Next**.



PASSWORD UNLOCKER

Enjoy to Use Password Reset and Password Recovery Tools



2). Set a new password for the selected user account. You can also modify the account properties. .



PASSWORD UNLOCKER

Enjoy to Use Password Reset and Password Recovery Tools



3). Click **Reboot** to restart computer and log into the user account with the new password. You can also click **OK** to return to the main interface for other jobs.

Note: Please remove the bootable disk before Windows restarts.



PASSWORD UNLOCKER

Enjoy to Use Password Reset and Password Recovery Tools



Option 3: Create a New Admin Account - If you decide to create a new admin account to access Windows again, please do as follows:

1). Select **Create a New Admin Account** and then click **Next**.



PASSWORD UNLOCKER

Enjoy to Use Password Reset and Password Recovery Tools



2). Set the user name and password for the new admin account. You can also manage the account properties.



PASSWORD UNLOCKER

Enjoy to Use Password Reset and Password Recovery Tools



3). Click **Reboot** to restart computer and log into the new admin account. You can also click **OK** to return to the main interface for other jobs.

Note: Please remove the bootable disk before Windows restarts.



PASSWORD UNLOCKER

Enjoy to Use Password Reset and Password Recovery Tools



- **Reset Windows Domain Password**

1. Select operating system installation you want to reset password of.



PASSWORD UNLOCKER

Enjoy to Use Password Reset and Password Recovery Tools



2. Select an option to reset forgotten Windows domain admin and user password.


Option 1: Change Windows Domain Password - If you decide to change forgotten domain admin and user password, please do as follows:

1). Select target domain user account and **Change Domain Password**, then click **Next**.



PASSWORD UNLOCKER

Enjoy to Use Password Reset and Password Recovery Tools



2). Set a new password for the selected domain user account.

Note: The password must be at least 8 characters long and contain uppercase letters, lowercase letters and numbers.



PASSWORD UNLOCKER

Enjoy to Use Password Reset and Password Recovery Tools



3. Click **Reboot** to restart computer and log into the domain user account with the new password.

Note: Please remove the bootable disk before Windows restarts.



PASSWORD UNLOCKER

Enjoy to Use Password Reset and Password Recovery Tools



Option 2: Create a New Domain Admin Account - If you decide to create a new admin account to access Windows again, please do as follows:

1). Select **Create a New Admin Account** and then click **Next**.



PASSWORD UNLOCKER

Enjoy to Use Password Reset and Password Recovery Tools



2). Set the user name and password for the new domain admin account.

Note: The password must be at least 8 characters long and contain uppercase letters, lowercase letters and numbers



PASSWORD UNLOCKER

Enjoy to Use Password Reset and Password Recovery Tools



3. Click **Reboot** to restart computer and log into the new domain admin account.

Note: Please remove the bootable disk before Windows restarts.



PASSWORD UNLOCKER

Enjoy to Use Password Reset and Password Recovery Tools



Know more for **Windows Password Unlocker** from: <http://www.passwordunlocker.com/windows-password-recovery.html>